10/26/98

Ex.



$\rho_{wood} = 0.7 \times 10^3$ kg/m^3

What fraction (%) of wood is above water ?

Let m_{wood} = mass of wood

y = % above water

$$V_{wood} = \frac{m_w}{\rho_{wood}}$$

$$F_{buoy} = \rho_{water} \underbrace{(1-y)\frac{m_w}{\rho_{wood}}}_{\text{volume displaced}} \times g = m_w g = F_{down}$$

$$\therefore \quad 1 - y \approx \frac{\rho_w}{\rho_{water}} = \frac{.7 \times 10^3}{1 \times 10^3} = .7, \quad y = .3 = 30\%$$

Ex. Goodyear blimp



$m_{blimp} = 4250$ kg

5400 m^3 of helium gas

$\rho_{helium} = 0.178$ kg/m^3

Find $m_{load} = ?$

$$F_{buoy} = F_{down} = \left(m_{blimp} + m_{He} + m_{load}\right) g$$

F_{buoy}: $\rho_{air} \times 9.8 \times 5400 = 63509\ N$ (1.2 for ρ_{air})

m_{blimp}: 4250

m_{He}: 0.178×5400 (0.178 = ρ_{He}, 5400 = volume)

g: 9.8

$$\rightarrow m_{load} = 1263.3\ kg$$

So far we have considered

water in a tank

.... swimming pool

..

where the fluid is not <u>flowing</u>



water in a pipe

in a river

.....

here fluid is flowing

<u>fluid dynamics</u> to study fluids in motion

Consider fluid flow in a pipe:



imagine boundaries 1 and 2 at time 0

at time Δt, they move to 1' and 2'

pipe cross-section area at 1 = A_1

" " " " 2 = A_2

Volume of flow passing 1 } must = { Volume of flow passing 2

$A_1 \underbrace{\Delta l_1}_{v_1 \Delta t} = A_2 \underbrace{\Delta l_2}_{v_2 \Delta t}$

$\therefore$ $\boxed{A_1 v_1 = A_2 v_2}$ ← this is the important "continuity equation"

Ex.

$A_1 = 3\ cm^2$ $\quad A_2 = 1\ cm^2$

$v_1 = 8\ m/s$ $\quad v_2 = ?$

$A_1 v_1 = A_2 v_2$

3×10^{-4} $\quad 8$ $\quad 1 \times 10^{-4}$

$\therefore v_2 = 24\ m/s$

Bernoulli's equation important!

consider flow in a pipe



imagine boundaries 1 and 2

pressure p_1 > pressure p_2

$\Rightarrow$ 1 flows to 1', 2 to 2'

work done by p_1 and p_2

$$= F_1 \Delta l_1 - F_2 \Delta l_2 = p_1 A_1 \Delta l_1 - p_2 A_2 \Delta l_2$$

A_1 = pipe area at 1

A_2 = " " " 2

$$= (KE + PE)_{22'} - (KE + PE)_{11'}$$

$$= \frac{1}{2} m_{22'} v_2^2 + m_{22'} g y_2 - \frac{1}{2} m_{11'} v_1^2 - m_{11'} g y_1 \quad (*)$$

$m_{22'} = \rho A_2 l_2$, $m_{11'} = \rho A_1 l_1$

Volume of flow passing 1 = Volume of flow passing 2

i.e. $A_1 l_1 = A_2 l_2$

Hence ⊛ becomes

$$p_1 - p_2 = \frac{1}{2}\rho v_2^2 + \rho g y_2 - \frac{1}{2}\rho v_1^2 - \rho g y_1$$

rearrang

$$\boxed{p_1 + \frac{1}{2}\rho v_1^2 + \rho g y_1 = p_2 + \frac{1}{2}\rho v_2^2 + \rho g y_2}$$

Bernoulli's eq

p_a $\quad \frac{kg}{m^3}$ $\quad 9.8$ $\quad m$

Ex.



pipe diameter at 1 = d_1 = 4 cm

" " " 2 = d_2 = 2 cm

$p_1 = 15 \times 10^5$ Pa

$v_1 = 12$ m/s

find p_2, v_2

continuity eq: $A_1 v_1 = A_2 v_2$

$A_1 = \pi d_1^2$, $A_2 = \pi d_2^2$

$\pi d_1^2 = \pi (4 \times 10^{-2})^2$ $\quad = \pi (2 \times 10^{-2})^2$

$\therefore v_2 = 48$ m/s

now use Bernoulli's eq

$$p_1 + \frac{1}{2}\rho v_1^2 + \rho g y_1 = p_2 + \frac{1}{2}\rho v_2^2 + \rho g y_2$$

p_1: 15×10^5 — $\frac{1}{2}\rho v_1^2$: 1000, 12^2 → 72000 — $\rho g y_1$: 1000, 9.8, 3 → 29400

p_2 — $\frac{1}{2}\rho v_2^2$: 1000, 48^2 → 11.52×10^5 — $\rho g y_2$: 1000, 9.8, 1.5 → 14700

$\therefore\ p_2 \simeq 4.35\times10^5\ p_a$, much less than p_1

Ex.



big water tank

$A_1 = 4\ m^2$

↑ tank area at 1

$A_2 = 2\ cm^2$

spigot area

$y_1 = 5\ m$

$y_2 = 1.6\ m$

find R

$$p_1 + \rho g y_1 + \frac{1}{2}\rho v_1^2 = p_2 + \rho g y_2 + \frac{1}{2}\rho v_2^2 \quad (1)$$

$p_1 = p_{atm}$ ← cancel → $p_2 = p_{atm}$

continuity: $A_1 v_1 = A_2 v_2$

4 — 2×10^{-4}

$\therefore\ v_2 = 2\times10^4\ v_1$

$v_2 >> v_1$

can drop $\frac{1}{2}\rho v_1^2$

Hence ① becomes

$$\rho g (y_1 - y_2) = \frac{1}{2} \rho v_2^2$$

$$v_2 = \sqrt{2g(y_1 - y_2)} = 8.16 \text{ m/s} = v_{\text{horizontal}}$$

$9.8 \quad 5 \quad 1.6$

range: $R = v_{\text{horizontal}} \times t_{23}$

$8.16 \quad .57$

$= 4.66 \text{ m}$

$$t_{23} = \sqrt{\frac{2y_2}{g}} \quad \begin{matrix} \leftarrow 1.6 \\ \leftarrow 9.8 \end{matrix}$$

$= .57 \text{ sec}$

---

important applications of Bernoulli's eq:

Air plane

how it flies ?



Bernoulli →

$$\left(p + \rho g y + \frac{1}{2} \rho v^2\right)_{\text{above}} = \left(p + \rho g y + \frac{1}{2} \rho v^2\right)_{\text{below}}$$

(1)

$y_{\text{above}} \approx y_{\text{below}}$ cancel

Wing is specially shaped, so that

$$v_{\text{above}} > v_{\text{below}}$$

Thus from ① we have $p_{below} > p_{above}$



area of wing = A

$F_{net} = F_{up} - F_{down}$

$= p_{below} \times A - p_{above} \times A$

airplane "floats" in air !

sinker ball



how he did it ? he puts top-spin ↻ as shown



$v_{above} < v_{below}$

$\therefore p_{above} > p_{below} \Rightarrow$ ball curves down

ideal flow

here things are so nice
(flowers, nice beach, all A⁺'s ...)

sprinkle some ink to a flow, see beautiful streamlines.



called laminar flow

real-life flow

here things are disgusting!
(exams, income tax ...)

flow has friction viscosity turbulence



no more orderly, beautiful streamlines



$\eta_{water} \ll \eta_{honey}$

η (eta) ≡ viscosity

↑ unit is [Pascal-sec]

Wed

Poiseulli's equation he was a medical doctor, studying blood flow in blood vessels.



consider a segment of artery

$P_1 > P_2$, blood flows from 1 to 2

Q = rate of flow $[m^3/sec]$

expect $(P_1 - P_2)$ larger → Q larger

R longer → Q more

he found

$$Q = \frac{\pi R^4}{8 \eta \ell} (P_1 - P_2)$$

note: R^4

area $A = \pi R^2$

m^3/sec ↑ Q

$Pa\text{-}sec$ ↑ η

m ↑ ℓ

Pa ↑ $(P_1 - P_2)$

material	η (viscosity) at 20°C (room temp)
oil (motor)	0.9
water	1.0×10^{-3}
blood	3.0×10^{-3}

Ex. high blood pressure

healthy person



needs $Q = 10^{-6}$ m³/sec

$\Delta p = p_1 - p_2 = 2.1$ Pa

$r = .4 \times 10^{-3}$ m

clogged vein



$r' = .35 \times 10^{-3}$ m

needs same Q

$\Delta p'_{clog} = ?$

$$Q = \frac{\pi r^4}{8 \eta \ell} \Delta p = \frac{\pi r'^4}{8 \eta \ell} \Delta p'$$

$$\therefore \Delta p' = \left(\frac{.4}{.35}\right)^4 \times 2.1 = 3.58 \text{ Pa}$$

↑ much bigger than 2.1

heart has to work much harder → high blood pressure

Chap. 10 mainly spring and SHM — motion — simple harmonic

Spring



$\ell_{original}$ ← neither stretched nor compressed



← apply a pulling force F

ℓ_{new}

$\ell_{new} - \ell_{original}$ = stretch $\equiv x$

suppose we try

F [N]	0	2	4	8	0
x [m]	0	.01	.02	.04	0

↑ when force removed, spring resumes original length

⇒ spring is elastic

But when F is too big, spring is ruined,



└ in this case, spring will not shrink back

to its original shape, because we have exceeded its

elastic limit

For moderate force (i.e. within elastic limit), we have

$F = kx$ Hooke's law

F = applied force

$x = \ell_{new} - \ell_{original}$

k: N, spring constant, N/m



Ex. $k = 5$ N/m, $x = .3$



$F = ?$

$F = 5 \times .3 = 1.5$ N

direction in ⟹

Ex. $k = 8$ N/m, $x = -.3$

note signs



$F = kx = 8 \times (-.3)$

$= -2.4$ N

direction in ⟸

See $F = kx$ is applicable to both stretching and compressing of spring

Ex.



$k = 150$ N/m

$l_{orig} = 1.2$ m

mass m is hung

$m = 4$ kg

find $l_{new} = ?$

$F = ky$

4×9.8 $\quad$ 150

$\therefore y = 0.26$ m

$l_{new} = l_{orig} + y$

$= 1.2 + .26 = 1.46$ m

Ex. two springs :



Find $l_{new} = ?$

Note spring-1 and spring-2 are subject to same force mg

$\therefore \quad F = mg = 6 \times 9.8 = k_1 y_1 \quad (k_1 = 400) \quad \rightarrow y_1 = .147$ m

also $\quad F = mg = 6 \times 9.8 = k_2 y_2 \quad (k_2 = 180) \quad \rightarrow y_2 = .327$ m

$$l_{new} = l_{orig} + y_1 + y_2 = .8 + .147 + .327 = 1.274\ m$$

---

2 spring in general:



x_1 = stretch of spring-1

x_2 = ------ spring-2

Spring-1 is subject to force F, $\therefore \quad F = k_1 x_1$ -- (1)

Spring-2 is also ----------, $\therefore \quad F = k_2 x_2$ -- (2)

$$(1),(2) \Rightarrow (x_1 + x_2) = \frac{1}{k_1} F + \frac{1}{k_2} F = \left(\frac{1}{k_1} + \frac{1}{k_2}\right) F$$

$$= \frac{F}{\left(\frac{1}{k_1} + \frac{1}{k_2}\right)^{-1}} \quad \cdots (3)$$

rename $x_{tot} = x_1 + x_2$, $\quad k_{tot} = \left(\frac{1}{k_1} + \frac{1}{k_2}\right)^{-1}$

or $\frac{1}{k_{tot}} = \frac{1}{k_1} + \frac{1}{k_2}$

(3) becomes $F = k_{tot}\, x_{tot}$

k_{tot} is also called $k_{effective}$

Summary



is same as one spring  with k_{eff}